


- 
- **Introduction**
 - **Distributed Prog. Paradigms**
 - **Distributed Object Technologies**
 - **Language Dependent: Ada 95**
 - **Language Independent: CORBA**

Ada 95 Distributed Systems Annex

Ada 95 Distributed Programming



A partition comprises one or more Ada packages

Supported Paradigms

- Client/Server Paradigm (RPC)
 - Synchronous / Asynchronous
 - Static / Dynamic
- Distributed Objects
- Shared Memory

Ada Distributed Application

- No need for a separate interfacing language as in CORBA (IDL)
 - Ada is the IDL
- Some packages categorized using pragmas
 - Remote_Call_Interface (RCI)
 - Remote_Types
 - Shared_Passive (SP)
- All packages except RCI & SP duplicated on partitions using them

Remote_Call_Interface (RCI)

- Allows subprograms to be called remotely
 - Statically bound RPCs
 - Dynamically bound RPCs
(remote access to subprogram)

Remote_Types

- Allows the definition of a remote access types
 - Remote access to subprogram
 - Remote reference to objects
(ability to do dynamically dispatching calls across the network)

Shared_Passive

- A Shared_Passive package contains variables that can be accessed from distinct partitions
- Allows support of shared distributed memory
- Allows persistence on some implementations

Building a Distributed App in Ada 95

1. Write app as if non distributed.
2. Identify remote procedures, shared variables, and distributed objects & **categorize** packages.
3. Build & test non-distributed application.
4. Write a configuration file for **partitioning** your app.
5. Build partitions & test distributed app.



Remote_Call_Interface

An Example

Write App

```
package Types is  
  type Device is (Furnace, Boiler,....);  
  type Pressure is ...;  
  type Temperature is ...;  
end Types;
```

```
with Types; use Types;  
package Sensors is  
  function Get_P (D: Device) return Pressure;  
  function Get_T (D: Device) return Temperature;  
end Sensors;
```

```
with Types; use Types;  
with Sensors;  
procedure Client_1 is  
  P := Sensors.Get_P (Boiler);
```

```
with Types; use Types;  
with Sensors;  
procedure Client_2 is  
  T := Sensors.Get_T (Furnace);
```

Categorize

```
package Types is
  pragma Pure;
  type Device is (Furnace, Boiler,...);
  type Pressure is ...;
  type Temperature is ...;
end Types;
```

```
with Types; use Types;
package Sensors is
  pragma Remote_Call_Interface;
  function Get_P (D:Device) return Pressure;
  function Get_T (D:Device) return Temperature;
end Sensors;
```

```
with Types; use Types;
with Sensors;
procedure Client_1 is
  P := Sensors.Get_P (Boiler);
```

```
with Types; use Types;
with Sensors;
procedure Client_2 is
  T := Sensors.Get_T (Furnace);
```

Build & Test

```
package Types is
  pragma Pure;
  type Device is (Furnace, Boiler,...);
  type Pressure is ...;
  type Temperature is ...;
end Types;
```

```
with Types; use Types;
package Sensors is
  pragma Remote_Call_Interface;
  function Get_P (D:Device) return Pressure;
  function Get_T (D:Device) return Temperature;
end Sensors;
```

```
with Types; use Types;
with Sensors;
procedure Client_1 is
  P := Sensors.Get_P (Boiler);
```

Build & Test

```
package Types is
  pragma Pure;
  type Device is (Furnace, Boiler,...);
  type Pressure is ...;
  type Temperature is ...;
end Types;
```




```
with Types; use Types;
package Sensors is
  pragma Remote_Call_Interface;
  function Get_P (D:Device) return Pressure;
  function Get_T (D:Device) return Temperature;
end Sensors;
```

```
with Types; use Types;
with Sensors;
procedure Client_2 is
  T := Sensors.Get_T (Furnace);
```

Partition




```
configuration Config_1 is  
  Node_A : Partition := (Sensors);  
  Node_B : Partition := (Client_1);  
  Node_C : Partition := (Client_2);  
end Config_1;
```

Partition




```
package Types is
  pragma Pure;
  type Device is ...;
  type Pressure is ...;
  type Temperature is ...;
end Types;
```

DUPLICATED




```
with Types; use Types;  
package Sensors is
```

```
  pragma Remote_Call_Interface;
```



```
  function Get_P(...) return Pressure;
```

```
  function Get_T(...) return Temperature;
```

```
end Sensors;
```



STUBS




```
with Types; use Types;  
package Sensors is
```

```
  pragma Remote_Call_Interface;
```

```
  function Get_P(...) return Pressure;
```



```
  function Get_T(...) return Temperature;
```

```
end Sensors;
```



SKELETON

+ BODY



```
.....:= Sensors.Get_P (Boiler);
```

Sensors.Get_P **Stub**

Marshal Arguments

Send

Node_B

Sensors.Get_P **body**

Select body

Skeleton

Unmarshal Arguments

Receive

Node_A

Asynchronous Calls

```
with Types; use Types;  
package Sensors is  
  pragma Remote_Call_Interface;  
  ...  
  procedure Log (D : Device; P : Pressure);  
  pragma Asynchronous (Log);  
end Bank;
```

- + returns immediately
- + exceptions are lost
- + parameters must be in

Remote_Types

An Example

Write App

```
package Alerts is
  type Alert is abstract tagged private;
  type Alert_Ref is access all Alert'Class;
  procedure Handle (A : access Alert);
  procedure Log (A : access Alert) is abstract;
private
  ...
end Alerts;
```

```
package Alerts.Pool is
  procedure Register (A : Alert_Ref);
  function Get_Alert return Alert_Ref;
end Medium;
```

```
with Alerts, Alerts.Pool; use Alerts;
procedure Process_Alerts is
begin
  loop
    Handle (Pool.Get_Alert);
  end loop;
end Process_Alerts;
```

```
package Alerts.Low is  
  type Low_Alert is new Alert with private;  
  procedure Log (A : access Low_Alert);  
private  
  ...  
end Alerts.Low;
```

```
with Alerts.Pool; use Alerts.Pool;  
package body Alerts.Low is  
  ...  
begin  
  Register (new Low_Alert);  
end Alerts.Low;
```



```
package Alerts.Medium is  
type Medium_Alert is new Alert with private;  
procedure Handle (A : access Medium_Alert);  
procedure Log (A : access Medium_Alert);  
private  
...  
end Alerts.Medium;
```

```
with Alerts.Pool; use Alerts.Pool;  
package body Alerts.Medium is  
...  
begin  
  Register (new Medium_Alert);  
end Alerts.Medium;
```

Categorize

```
package Alerts is
  pragma Remote_Types;
  type Alert is abstract tagged private;
  type Alert_Ref is access all Alert'Class;
  procedure Handle (A : access Alert);
  procedure Log (A : access Alert) is abstract;
private
```

```
package Alerts.Pool is
  pragma Remote_Call_Interface;
  procedure Register (A : Alert_Ref);
  function Get_Alert return Alert_Ref;
end Medium;
```

```
with Alerts, Alerts.Pool; use Alerts;
procedure Process_Alerts is
begin
  loop
    Handle (Pool.Get_Alert);
  end loop;
end Process_Alerts;
```

```
package Alerts.Low is
  pragma Remote_Types;
  type Low_Alert is new Alert with private;
  procedure Log (A : access Low_Alert);
private
  ...
end Alerts.Low;
```

```
package Alerts.Medium is
  pragma Remote_Types;
  type Medium_Alert is new Alert with private;
  procedure Handle (A : access Medium_Alert);
  procedure Log (A : access Medium_Alert);
private
  ...
end Alerts.Medium;
```

Build & Test

```
package Alerts is
  pragma Remote_Types;
  type Alert is abstract tagged private;
  type Alert_Ref is access all Alert'Class;
  procedure Handle (A : access Alert);
  procedure Log (A : access Alert) is abstract;
private
  ...
end Alerts;
```

```
package Alerts.Low is
  pragma Remote_Types;
  type Low_Alert is new Alert with private;
  procedure Log (A : access Low_Alert);
private
  ...
end Alerts.Low;
```

```
package Alerts.Medium is
  pragma Remote_Types;
  type Medium_Alert is new Alert with private;
  procedure Handle (A : access Medium_Alert);
  procedure Log (A : access Medium_Alert);
private
  ...
end Alerts.Medium;
```

```
package Alerts.Pool is
  pragma Remote_Call_Interface;
  procedure Register (A : Alert_Ref);
  function Get_Alert return Alert_Ref;
end Medium;
```

```
with Alerts, Alerts.Pool; use Alerts;
procedure Process_Alerts is
begin
  loop
    Handle (Pool.Get_Alert);
  end loop;
end Process_Alerts;
```

Partition

```
configuration Config_2 is  
Node_AL : Partition := (Alerts.Low);  
Node_AM : Partition := (Alerts.Medium);  
Node_B  : Partition := (Alerts.Pool);  
Node_C  : Partition := (Process_Alerts);  
end Config_2;
```

What Happens When Executing the Distributed Program ?

```

package Alerts.Low is
  pragma Remote_Types;
  type Low_Alert is new Alert with private;
  procedure Log (A : access Low_Alert);
private
  ...
end Alerts.Low;

```

Node_AL

```

package Alerts.Medium is
  pragma Remote_Types;
  type Medium_Alert is new Alert with private;
  procedure Handle (A : access Medium_Alert);
  procedure Log (A : access Medium_Alert);
private
  ...
end Alerts.Medium;

```

Node_AM

Step 1: A Low_Alert object in Node_AL registers itself with Node_B

```

package Alerts.Pool is
  pragma Remote_Call_Interface;
  procedure Register (A : Alert_Ref);
  function Get_Alert return Alert_Ref;
end Medium;

```

Node_B

```

with Alerts, Alerts.Pool; use Alerts;
procedure Process_Alerts is
begin
  loop
    Handle (Pool.Get_Alert);
  end loop;
end Process_Alerts;

```

Node_C

```

package Alerts.Low is
  pragma Remote_Types;
  type Low_Alert is new Alert with private;
  procedure Log (A : access Low_Alert);
private
  ...
end Alerts.Low;

```

Node_AL

```

package Alerts.Medium is
  pragma Remote_Types;
  type Medium_Alert is new Alert with private;
  procedure Handle (A : access Medium_Alert);
  procedure Log (A : access Medium_Alert);
private
  ...
end Alerts.Medium;

```

Node_AM

Step 2: A Medium_Alert object in Node_AM registers itself with Node_B

```

package Alerts.Pool is
  pragma Remote_Call_Interface;
  procedure Register (A : Alert_Ref);
  function Get_Alert return Alert_Ref;
end Medium;

```

Node_B

```

with Alerts, Alerts.Pool; use Alerts;
procedure Process_Alerts is
begin
  loop
    Handle (Pool.Get_Alert);
  end loop;
end Process_Alerts;

```

Node_C


```
package Alerts.Low is
```

```
  pragma Remote_Types;
```

```
  type Low_Alert is new Alert with private;
```

```
  procedure Log (A : access Low_Alert);
```

```
private
```

```
  ...
```

```
end Alerts.Low;
```

Node_AL

```
package Alerts.Medium is
```

```
  pragma Remote_Types;
```

```
  type Medium_Alert is new Alert with private;
```

```
  procedure Handle (A : access Medium_Alert);
```

```
  procedure Log (A : access Medium_Alert);
```

```
private
```

```
  ...
```

```
end Alerts.Medium;
```

Node_AM

Step 3: Process_Alerts in Node_C does an RPC to Get_Alert in Node_B

```
package Alerts.Pool is
```

```
  pragma Remote_Call_Interface;
```

```
  procedure Register (A : Alert_Ref);
```

```
  function Get_Alert return Alert_Ref;
```

```
end Medium;
```

Node_B

```
with Alerts, Alerts.Pool; use Alerts;
```

```
procedure Process_Alerts is
```

```
begin
```

```
  loop
```

```
    Handle (Pool.Get_Alert);
```

```
  end loop;
```

```
end Process_Alerts;
```

Node_C

```
package Alerts.Low is
```

```
  pragma Remote_Types;
```

```
  type Low_Alert is new Alert with private;
```

```
  procedure Log (A : access Low_Alert);
```

```
private
```

```
  ...
```

```
end Alerts.Low;
```

Node_AL

```
package Alerts.Medium is
```

```
  pragma Remote_Types;
```

```
  type Medium_Alert is new Alert with private;
```

```
  procedure Handle (A : access Medium_Alert);
```

```
  procedure Log (A : access Medium_Alert);
```

```
private
```

```
  ...
```

```
end Alerts.Medium;
```

Node_AM

Step 4: Get_Alert returns a pointer to an Alert object (Low_Alert or Medium_Alert)

```
package Alerts.Pool is
```

```
  pragma Remote_Call_Interface;
```

```
  procedure Register (A : Alert_Ref);
```

```
  function Get_Alert return Alert_Ref;
```

```
end Medium;
```

Node_B

```
with Alerts, Alerts.Pool; use Alerts;
```

```
procedure Process_Alerts is
```

```
begin
```

```
  loop
```

```
    Handle (Pool.Get_Alert);
```

```
  end loop;
```

```
end Process_Alerts;
```

Node_C

```

package Alerts.Low is
  pragma Remote_Types;
  type Low_Alert is new Alert with private;
  procedure Log (A : access Low_Alert);
private
  ...
end Alerts.Low;

```

Node_AL ?

```

package Alerts.Medium is
  pragma Remote_Types;
  type Medium_Alert is new Alert with private;
  procedure Handle (A : access Medium_Alert);
  procedure Log (A : access Medium_Alert);
private
  ...
end Alerts.Medium;

```

Node_AM

Step 5: Node_C performs a dispatching RPC. It calls Handle in Node_AL or Node_AM

```

package Alerts.Pool is
  pragma Remote_Call_Interface;
  procedure Register (A : Alert_Ref);
  function Get_Alert return Alert_Ref;
end Medium;

```

Node_B


```

with Alerts.Pool; use Alerts;
procedure Process_Alerts is
begin
  loop
    Handle (Pool.Get_Alert);
  end loop;
end Process_Alerts;

```

Node_C

What Does Get_Alert Return ?



Remote Access to Class Wide Type

- **At compile time:**
 - **You do not know what operation you'll dispatch to**
 - **On what node that operations will be executed on**